


802.1x Windows 7

If this is the first time that the computer is connected via 802.1x authentication must enable the service.


Enabling the service

- Click the Start button in the Search box, type **services.msc** and then press ENTER.
- On the Services tab that opens, look for the service named **Wired AutoConfig** right-click and select **Properties**.
- Change the item **Startup type** from *Manual* to **Automatic**.
- If the service status is *Stopped*, click on the **Start** button.




Settings Supplicant 802.1x

- Open the settings for the network adapter: DX-click on the icon of the LAN connection (lower right) then select *Open Network and Sharing Center*, click on *Change adapter setting*.
- DX-click on the connection for which you want to enable 802.1x authentication then select **Properties**.
- Click on tab **Authentication** and then select the check boxes:
 - *Enable IEEE 802.1X authentication*,
 - *Remember my credentials....*,
 - *Fallback to unauthorized....*



- Click on the button **Settings** and on the Protected EAP Properties window that appears check that:
 - is checked *Validate server certificate* choosing from the *Trusted Root Certification Authorities* the voice *AddTrust External CA Root*,
 - is checked *Connect to these servers* stating the following (separated by ;) *nps1.unitn.it;nps2.unitn.it;nps3.unitn.it*,
 - the authentication method selected is *Secured password (EAP-MSCHAP v2)*.




The following configuration is required only for PC **NOT in the unitn domain** (for PC in the unitn domain skip this step)


* Click the Configure button, then from the Properties window that appears EAP MASCHAPv2 **de**select the item //Automatically use....// as shown below:



- Click the button **Additional Settings...** for the tab **Properties - Local Area Connection (LAN)** and on the tab **Advanced setting** that will appear check:
 - that the item *Specify authentication mode* is checked, choosing among:
 - *User authentication* (For computer **NOT** in UNITN domain)
 - *User or computer authentication* (For computer in UNITN domain)
 - click on the button **Save Credetials**



- After connecting the network cable when prompted, enter your unitn credentials




In the event that the credentials are not recognized you will be automatically redirected to a Captive Portal authentication.

Problems

Force the reauthentication:

- Unselect *Remember my credentials...* then deactivate/activate the network card:



From:

<https://wiki.unitn.it/> - **Wiki UniTn**

Permanent link:

<https://wiki.unitn.it/pub:win-7-en?rev=1382437114>

Last update: **2013/10/22 10:18**

